

Natives buttons categories from Accengage

List of templates for buttons categories from Accengage.

English	French	Category value
Yes/No	Oui/Non	yes_no_category
:o) / :o(:o) / :o(happy_unhappy_category
Yes / Later	Oui / Plus tard	yes_later_category
Accept / Decline	Accepter / Refuser	accept_decline_category
Accept / Later	Accepter / Plus tard	accept_later_category
I agree / I disagree	D'accord / Pas d'accord	agree_disagree_category
Satisfied / Unsatisfied	Satisfait / Non satisfait	satisfied_unsatisfied_category
Buy now / Later	J'achète / Plus tard	buy_later_category
Show me / Share	Voir l'article / Partager	show_share_category
Share / Later	Partager / Plus tard	share_later_category
Add to wishlist / Later	Mettre en favoris / Plus tard	favorite_later_category
Show offer / Share	Voir l'offre / Partager	offer_share_category
Show the deal / Later	Voir le deal / Plus tard	deal_later_category
Enjoy now / No thanks	En profiter / Non merci	enjoy_nothanks_category
Add to cart / No thanks	Ajouter au panier / Non merci	addcart_nothanks_category
Show cart / Later	Voir mon panier / Plus tard	showcart_later_category
Access booking / Later	Voir ma réservation / Plus tard	showbooking_later_category
Access details / Later	Voir mon billet / Plus tard	showticket_later_category
Man / Woman	Homme / Femme	man_woman_category
Show me / Close	Afficher / Fermer	show_close_category
Share / No thanks	Partager / Non merci	share_nothanks_category
Open / Close	Ouvrir / Fermer	open_close_category
Like / Later	J'aime / Plus tard	like_later_category
Like / Dislike	J'aime / Je n'aime pas	like_dislike_category
Subscribe / No thanks	S'abonner / Non merci	subscribe_nothanks_category
Subscribe / Cancel	S'inscrire / Annuler	register_cancel_category
Login / Close	Se connecter / Fermer	login_close_category
Create an account / Close	Créer un compte / Fermer	createaccount_close_category

Get more / Get less	Recevoir plus / Recevoir moins	getmore_getless_category
Get more / No thanks	Recevoir plus / Non	getmore_no_category
Call / Later	Appeler / Plus tard	call_later_category
Add to calendar / Close	Ajouter au calendrier / Fermer	addcalendar_close_category
Answer it / Close	Répondre / Fermer	answer_close_category
Take part / Close	Participer / Fermer	takepart_close_category
Give a feedback / No thanks	Donner mon avis / Non merci	givefeedback_nothanks_category
Rate the app / Later	Noter l'application / Plus tard	rate_later_category
I have a feedback / Later	Améliorer l'application / Plus tard	havefeedback_later_category
See more / Close	En savoir plus / Fermer	seemore_close_category
Search / Close	Rechercher / Fermer	search_close_category
Find / Close	Découvrir / Fermer	find_close_category
Read / Close	Consulter / Fermer	read_close_category
Let's go / Close	J'y vais / Fermer	letsgo_close_category
I'm in / No thanks	J'en suis / Non merci	imin_nothanks_category

The possible action for buttons (both Android and iOS) are `browser`, `email`, `phone`, `store`, `sms`, `urlscheme`, `webview`, and `close`. For iOS, you can also use `request`.

Here are the effects of the different actions :

1. `browser`: Open the given url into the device's browser;
2. `email`: Open the email application on the device;
3. `phone`: Open the phone application;
4. `store`: Open the Play Store/Apple Store on the given url;
5. `sms`: Open the SMS application;
6. `urlscheme`: Deep link into your application;
7. `webview`: Open the given url;
8. `request`: Can send an url to the application if the application is able to receive background informations and the user's device authorizes background communications;
9. `close`: Does not open the application and delete the notification;

For iOS, buttons with `background` type can only have actions "request" or "close". By default, the second buttons for each native template (except `show_share_category`, `offer_share_category` and `man_woman_category`) have the type `background`.